

IBSNOW: FAQ



New IoT Bridge for Snowflake Available

This document covers v2.0.0 and older versions of IoT Bridge for Snowflake. It now ships as part of Chariot. To see the latest IoT Bridge for Snowflake documentation, go to [IoT Bridge for Snowflake in Chariot](#).

General

[I am interested in IoT Bridge for Snowflake. How do I set it up?](#)

[How do I find my Azure Marketplace Billing ID](#)

[Where can I get more information on MQTT Transmission and setting it up?](#)

[I have a logging error of "Failed to load the private key based on <PRIVATE KEY>"](#)

[I have a warning error of "400 Status"](#)

[Is the Ingestion able to handle a UNS Topic Namespace or only Sparkplug B?](#)

Currently, only Sparkplug B is supported

[Where can we find the machine models data?](#)

All machine models can be found in the `NODE_MACHINE_REGISTRY_VW` view

[How does the `snowflake\_streaming\_channel\_scheme = EDGE\_ID` work?](#)

The channel scheme setting defines how IBSNOW connects to the Snowflake streaming endpoint. A channel represents a logical, named streaming connection to Snowflake. When you choose `EDGE_ID` as your channel scheme, IBSNOW will make a separate connections to the Snowflake streaming endpoint for each unique Sparkplug edge node.

[Why are my `SPARKPLUG\_DEVICE\_MESSAGES` table and `NODE\_MACHINE\_REGISTRY\_VW` view empty?](#)

If you are not publishing MQTT Sparkplug messages formatted using Sparkplug templates, these will not be populated as the templates are used to create and maintain the `NODE_MACHINE_REGISTRY_VW` view. The payload will be present in the `SPARKPLUG_RAW` table.

If you are using Ignition and MQTT Transmission, you will need to ensure that your Transmitter is configured with Convert UDTs set to False

[Are Edge Level UDTs supported?](#)

Currently only device level UDTs are supported.

[How do I increase the max heap / max memory allocation for the IoT Bridge?](#)

Update the following configuration option in `/opt/ibsnow/yajsw/conf/wrapper.conf` (default is 1024MB)

`wrapper.java.additional.4 = -Xmx1024m`

[I have data in the `SPARKPLUG\_RAW` table but not in the `SPARKPLUG\_DEVICE\_MESSAGES` table](#)

The most common cause is that the stream on the source view is stale. Review the [Stream Staleness](#) document on identifying, correcting and avoid future stream staleness

[Azure Marketplace offering fails to deploy with subscription error](#)

[I am not getting data uploaded to Snowflake](#)

If you are failing to upload data to Snowflake, check the common items below:

- Review our [config docs](#) and sanity check your configuration
- Make sure Ingest user doesn't have 'must change password' set to true
- Ingest user has been granted the `CL_BRIDGE_PROCESS_RL` role

[I am seeing "Throttled due to memory pressure" warnings in the log](#)

The usual cause for this error is that Snowflake is throttling the data throughput because too much data is trying to be pushed through too few channels.

By default, in the [ibsnow.properties configuration file](#), we use `'snowflake_streaming_channel_scheme = EDGE_ID'` which means there is a channel per Sparkplug Edge Node.

We can increase the number of 'streaming channels' available for pushing to Snowflake streaming ingest services by modifying the schema to read `'snowflake_streaming_channel_scheme = DEVICE_ID'` which will create a channel on a per Sparkplug Device basis.

By increasing the number of channels, we should be able to increase the throughput and free up the memory backup.